

Slurm Batch System on HPCF and ECS

Alon Shtivelman,

Computing and Software Support Team

User Services Section

alon.shtivelman@ecmwf.int



Interactive vs Batch

• To run a script or a program **interactively**, enter the executable name and any necessary arguments at the system prompt.


```
$> ./your-program arg1 arg2
```

 You can also run your job in background so that other commands can be executed at the same time...


```
$> ./your-program arg1 arg2 &
$>
```



Interactive vs Batch








Computing (batch) nodes



Interactive vs Batch



Login node

Computing (batch) nodes




Batch system on Atos HPCF and ECS

- Formerly known as Simple Linux Utility for Resource Management (SLURM)
- Slurm: Cluster workload manager:
 - Framework to execute and monitor batch work
 - Resource allocation (where?)
 - Scheduling (when?)



 Batch job: shell script that will run unattended, with some special directives describing the job itself

Quality of Service (queues)





ECS Quality of Service (standard queues)

QoS	Туре	Suitable for	Shared nodes	Max jobs per user	Default / Max Wall Clock Limit	Default / Max CPUs	Default / Max Memory
ef	fractional	serial and small parallel jobs - DEFAULT	Yes	-	average job runtime + standard deviation / 2 days	1/8	8 GB / 16 GB
ei	interactive	serial and small parallel interactive jobs with ecinteractive	Yes	1	12 hours / 7 days	1 / 4	8 GB / 8 GB
el	long	Long-running serial and small parallel jobs	Yes	-	average job runtime + standard deviation / 7 days	1/8	8 GB / 16 GB
et	Time-critical Option 1	serial and small parallel Time-Critical jobs. Only usable through ECACCESS Time Critical Option-1	Yes	-	average job runtime + standard deviation / 12 hours	1/8	8 GB / 16 GB



Atos HPCF Quality of Service (standard queues)

QoS	Туре	Suitable for	Shared nodes	Max jobs per user	Default / Max Wall Clock Limit	Default / Max CPUs	Default / Max Memory
nf	fractional	serial and small parallel jobs - DEFAULT	Yes	-	average job runtime + standard deviation / 2 days	1 / 128	8 GB / 128 GB
ni	interactive	serial and small parallel interactive jobs with ecinteractive	Yes	1	12 hours / 7 days	1 / 32	8 GB / 32 GB
np	parallel	parallel jobs requiring more than half a node	No	-	average job runtime + standard deviation / 2 days	1/-	240GB per node (all usable mem)

https://confluence.ecmwf.int/x/ZBhbDg




Batch job script

- A job is typically a shell script
 - bash/ksh
- Directives are shell comments:
 - starting with #SBATCH
 - Lowercase only
 - No spaces in between
 - No variable expansion
- All directives are optional
 - System defaults in place

```
#!/bin/bash
# The job name
#SBATCH --job-name=helloworld
# Set the error and output files
#SBATCH --output=hello-%J.out
#SBATCH --error=hello-%J.out
# Set the initial working directory
#SBATCH --workdir=/scratch/userid
# Choose the queue
#SBATCH --gos=ef
# Wall clock time limit
#SBATCH --time=00:05:00
# Send an email on failure
#SBATCH --mail-type=FAIL
# This is the job
echo "Hello World!"
sleep 30
```

Submitting a job: sbatch

- **sbatch**: Submits a job to the system. Job is configured:
 - including the directives in the job script
 - using the same directives as command line options
- The job to be submitted can be specified:
 - As an argument of sbatch
 - If no script is passed as an argument, sbatch will read the job from standard input
- The corresponding job id will be returned if successful, or an error if the job could not be submitted





Submitting a job from cron


\$> ssh hpc-cron

\$> ssh ecs-cron

\$> crontab -e

\$> crontab -1

05 12 * * * sbatch -Q \$HOME/yourcronjob.sh



General job directives

Directive	Description	Default
job-name= -J	A descriptive name for the job	Script name
output= -o	Path to the file where standard output is redirected. Special placeholders for job id ($\%j$) and the execution node ($\%N$)	slurm-%j.out
error= -e	Path to the file where standard error is redirected. Special placeholders for job id ($\% j$) and the execution node ($\% N$)	output value
chdir= -D	Working directory of the job. The output and error files can be defined relative to this directory.	submitting dir
qos= -q	Quality of service (queue) where the job is to be submitted	nf on Atos HPCF ef on ECS
time= -t	Wall clock limit of the job (not cpu time limit!) Format: m, m:s, h:m:s, d-h, d-h:m or d-h:m:s	QoS default
mail-type= -m	Notify user by email when certain event types occur. Valid type values are NONE, BEGIN, END, FAIL, REQUEUE, and ALL	disabled
mail-user= -M	Email address to send the email	submit user
account= -A	Project account for the job where the usage will be accounted for. Relevant for HPCF only	Default user project account

https://confluence.ecmwf.int/x/WKrRAg



Resource allocation Job directives

Directive	Description	Default
nodes= -N	Number of nodes for the job	1
ntasks= -n	Number of tasks in the job (i.e. MPI tasks)	1
cpus-per-task= -c	Cpus to allocate per each tasks (i.e. threads, OpenMP)	1
tasks-per-node=	Tasks to allocate on each node. Useful for parallel tasks requiring considerable memory	fill the node
mem=	Memory per node	Partition Default
hint=multithread hint=nomultithread	Use Hyperthreading Don't use Hyperthreading	Hyperthreading enabled
gres=ssdtmp: <size>G</size>	Size of the TMPDIR on SSD (fractional jobs only)	3GB

https://confluence.ecmwf.int/x/WKrRAg




Some useful Slurm environment variables

Variable	Description
\$SLURM_JOB_ID	The Job ID.
\$SLURM_JOB_NODELIST	Contains the definition (list) of the nodes that is assigned to the job.
\$SLURM_CPUS_PER_TASK	Number of CPUs per task.
\$SLURM_MEM_PER_CPU	Memory per CPU. Same asmem-per-cpu .
\$SLURM_MEM_PER_NODE	Memory per node. Same asmem .
\$SLURM_NTASKS	Same as -n, –ntasks. The number of tasks.
\$SLURM_NTASKS_PER_NODE	Number of tasks requested per node.
\$SLURM_NNODES	Total number of nodes in the job's resource allocation.
\$SLURM_ARRAY_JOB_ID	Job array's master job ID number.
\$SLURM_ARRAY_TASK_ID	Job array ID (index) number.
\$SLURM_ARRAY_TASK_COUNT	Total number of tasks in a job array.
\$SLURM_ARRAY_TASK_MAX	Job array's maximum ID (index) number.
\$SLURM_ARRAY_TASK_MIN	Job array's minimum ID (index) number.

https://confluence.ecmwf.int/x/WKrRAg



Job States





Checking the queue: squeue

• squeue: displays information about the jobs currently running or waiting

Option	Description
me	View all my jobs
name <jobname> -n <jobname></jobname></jobname>	View all the jobs with the specified job name
state <state> -t <state></state></state>	View all the jobs that are in the specified state (i.e. PENDING/RUNNING)
qos <qos> -q <qos></qos></qos>	View all the jobs on the specified QoS
account <account> -A <account></account></account>	View all the jobs on the specified account
interactive -i	Interactive option: ask for confirmation before cancelling jobs
signal <signal> -s <signal></signal></signal>	Signal to send the job instead of SIGKILL

```
$> squeue --me

JOBID NAME USER QOS STATE TIME_LIMIT NODES FEATURES NODELIST(REASON)
64241519 helloworld usxa ef RUNNING 0:03 12:00:00 1 (null) aa6-203
```



Canceling a job: scancel

• The most common usage of scancel is:

\$> scancel <jobid1> <jobid2> <jobid3>

Option	Description			
me	Cancel all my jobs			
name <jobname> -n <jobname></jobname></jobname>	Cancel all my jobs with the specified job name			
state <state> -t <state></state></state>	Cancel all my jobs that are in the specified state (i.e. PENDING/RUNNING)			
qos <qos> -q <qos></qos></qos>	Cancel all my jobs on the specified QoS			
account <account> -A <account></account></account>	Cancel all my jobs on the specified account			
interactive -i	Interactive option: ask for confirmation before cancelling jobs			
signal <signal> -s <signal></signal></signal>	Signal to send the job instead of SIGKILL			



Canceling a job: scancel

- A job can be cancelled either if it is running or still waiting on the queue
- You will see a message like this in your job error output:

```
slurmstepd: error: *** JOB 64243399 ON ad6-203 CANCELLED AT 2023-10-24T13:41:02 ***
```



Why doesn't my job start?

Check the last column of the squeue output for a hint...

```
$> squeue -j 64243399

JOBID NAME USER QOS STATE TIME TIME_LIMIT NODES FEATURES NODELIST(REASON)
64243399 helloworld user ef PENDING 0:00 03:00:00 1 (null) (Priority)
```

Reason	Description
Priority	There are other jobs with more priority
Resources	No free resources are available
AssocMaxJobsLimit	You have reached a limit in the number of jobs you can submit to the system
QOSMaxJobsPerUserLimit	You have reached a limit in the number of jobs you can submit to a QoS
ReqNodeNotAvail	A System Session or outage may be going on. Check our service status on https://www.ecmwf.int/en/service-status

• man squeue for the complete list of reason codes



Checking limits

scontrol show partition [partition]

- Will show all partitions if a partition wasn't specified
- Default Wall Clock Time
- Default and Max Memory Per Node
- Overtime I imit

sacctmgr show qos

- Max Wall Clock Time
- Max Jobs Per User in the QoS
- Max Jobs Submitted Per User in the QoS
- Maximum Resources (TRES) allowed per Job

sacctmgr show assoc user=\$USER

- Maximum Jobs (in any state) per Association*
- Maximum Submitted Jobs per Association*

* Association (complex-partition-account-user)



Information about past and present jobs: sacct

• By default, **sacct** will return information about your jobs that started today

Option	Description
-j <jobid></jobid>	Show the job with that jobid
-u <user></user>	Show jobs for the specified user. Use option –a for all users
-E <endtime></endtime>	Show jobs eligible before that date and time
-S <starttime></starttime>	Show jobs eligible after that date and time
-s <statelist></statelist>	Show jobs on the states (comma-separated) given during the time period. Valids states are: CANCELLED, COMPLETED, FAILED, NODE_FAIL, RUNNING, PENDING, TIMEOUT
-q <qos></qos>	Show jobs only for the qos selected
-o <outformat></outformat>	Format option. Comma-separated names of fields to display
-е	Show the different columns to be used for the -o option
-X	Hide the job step information, showing the allocation only




Accounting – HPCF only

- Every job run on HPCF will be charged an amount of System Billing Units (SBUs)
 - ECS usage is not charged
- Check your project account in the job!
- Examples:
 - A serial job using 1 hour of elapsed time will be charged about 18.91 SBU.
 - A parallel job requesting 2 nodes, running for 3 hours elapsed time will be charged 14522.43 SBU.
- SBUs used by a job reported at the end of the job output
- Check your overall usage at HPC usage portal regularly:
 - https://hpc-usage.ecmwf.int/

https://confluence.ecmwf.int/x/NrgvEQ



```
[ECMWF-INFO -ecepilog]
[ECMWF-INFO -ecepilog] This is the ECMWF job Epilogue
[ECMWF-INFO -ecepilog] +++ Please report issues using the Support portal +++
[ECMWF-INFO -ecepilog] +++ https://support.ecmwf.int
[ECMWF-INFO -ecepilog]
[ECMWF-INFO -ecepilog] Run at 2022-08-24T09:09:01 on ac
[ECMWF-INFO -ecepilog] JobName
                                                 : myjob
[ECMWF-INFO -ecepilog] JobID
                                                 : 37015044
[ECMWF-INFO -ecepilog] Submit
                                                  : 2022-08-24T09:08:55
[ECMWF-INFO -ecepilog] Start
                                                  : 2022-08-24T09:08:55
[ECMWF-INFO -ecepilog] End
                                                 : 2022-08-24T09:09:01
[ECMWF-INFO -ecepilog] QueuedTime
                                                 : 0.0
[ECMWF-INFO -ecepilog] ElapsedRaw
                                                 : 6
[ECMWF-INFO -ecepilog] ExitCode
                                                 : 0:0
[ECMWF-INFO -ecepilog] DerivedExitCode
                                                 : 0:0
                                                 : COMPLETED
[ECMWF-INFO -ecepilog] State
[ECMWF-INFO -ecepilog] Account
                                                 : myaccount
[ECMWF-INFO -ecepilog] QOS
                                                 : np
[ECMWF-INFO -ecepilog] User
                                                 : user
[ECMWF-INFO -ecepilog] StdOut
                                                  : /home/user/slurm-37015044.out
[ECMWF-INFO -ecepilog] StdErr
                                                  : /home/user/slurm-37015044.out
[ECMWF-INFO -ecepilog] NNodes
[ECMWF-INFO -ecepilog] NCPUS
                                                 : 256
[ECMWF-INFO -ecepilog] SBU
                                                 : 4.083
[ECMWF-INFO -ecepilog]
```




Multi-complex setup

- One Slurm scheduler in each complex
- Sbatch may submit jobs to a different complex
 - System session or outage
- All the other standard Slurm commands will only show information about the local complex
- You may use multi-complex-enabled wrappers:
 - ecsqueue
 - ecscancel

Hint: First digit of Job ID indicates its complex

1... = AA, 2... = AB, 3... = AC, 4... = AD, 6... = ECS





Running parallel workloads: srun


- Spawn parallel applications within a job
- Similar options as sbatch for resources
- Geometry inherited from job by default
 - cpus-per-task must be always specified
- To be used for MPI, OpenMP or Hybrid
- CPU binding done by default

```
#!/bin/bash
#SBATCH --job-name=test-hybrid
#SBATCH --qos=np
#SBATCH --ntasks=128
#SBATCH --cpus-per-task=4
#SBATCH --hint=nomultithread
#SBATCH --time=10:00
#SBATCH --output=test-hybrid.%j.out
#SBATCH --error=test-hybrid.%j.out
# Ensure OpenMP correct pinning
export OMP PLACES=threads
srun -c $SLURM CPUS PER TASK my mpi openmp app
```

Use --hint=nomultithread to disable HyperThreading if not needed

Note for ECS users: Only small parallel jobs up to 8 CPUs may run on queue ef







Hands on time!

Training:

https://confluence.ecmwf.int/display/UDOC/Working+in+Batch+-+Atos+HPCF+and+ECS+Introduction+Tutorial Slurm documentation:

https://confluence.ecmwf.int/display/UDOC/HPC2020%3A+Writing+SLURM+jobs



