

ecCodes BUFR Command-Line Interface (CLI) Tools

Chris Kelly

Software Engineer, Observations Team

christopher.kelly@ecmwf.int



CLI tools vs. Python interface

- ecCodes BUFR includes both CLI tools & a Python interface

Command-Line Interface	Python Interface
<ul style="list-style-type: none">• Rapid file inspection and filtering	<ul style="list-style-type: none">• Complex data integration and analysis
<ul style="list-style-type: none">• On-the-fly modifications	<ul style="list-style-type: none">• Complete observation processing pipeline
<ul style="list-style-type: none">• Batch quality checks	<ul style="list-style-type: none">• Sophisticated quality control
<ul style="list-style-type: none">• Lightweight regression testing	<ul style="list-style-type: none">• Reproducible scientific workflows

Key functions of CLI tools

- Examine BUFR file/message structure and contents
→ **bufr_count**, **bufr_ls**, **bufr_dump**
- Copy BUFR file content
→ **bufr_copy**
- Simple data retrievals and modifications
→ **bufr_get**, **bufr_set**
- Advanced data retrievals and modifications
→ **bufr_filter**
- Compare BUFR messages contained in two files
→ **bufr_compare**

Example data access

- Global Upper Air Radiosonde BUFR archive from ECMWF
 - **Search:** `gov.noaa.ncdc:C01549`
 - **Download:** `Upperair-BUFR_ECMWF_d202201_c20250206.tar.gz` (1.7 GB)



The screenshot shows the NOAA National Centers for Environmental Information website. The header includes the NOAA logo and the text "National Centers for Environmental Information" and "NATIONAL OCEANIC AND ATMOSPHERIC ADMINISTRATION". Below the header is a navigation bar with links: Home, Products, Services, Resources, News, About, Contact. The main content area is titled "Global Upper Air Radiosonde Binary Universal Form for the Representation of meteorological data (BUFR) archive from ECMWF". Below this title is a sub-header "Upper air BUFR - ECMWF". To the left of the text is the NOAA logo. To the right of the text is a description of the dataset: "This is a dataset of high resolution upper air soundings collected by European Centre for Medium-Range Weather Forecasts (ECMWF) in the World Meteorological Organization's (WMO) Binary Universal Form for the Representation of meteorological data (BUFR) format. The parameters and metadata captured at each level contain time displacement, latitude displacement, longitude displacement, geopotential height, pressure, temperature, dew point temperature, wind speed, wind direction, level". To the right of the text is a table with two rows: "Dataset Citation" and "Dataset Identifiers". The "Dataset Citation" row contains the text "Cite this dataset when used as a source." and the "Dataset Identifiers" row contains the text "ISO 19115-2 Metadata".

NOAA Data

- **Citation:** *Xungang Yin; DOC/NOAA/NESDIS/NCEI > National Centers for Environmental Information, NESDIS, NOAA, U.S. Department of Commerce*

Examine BUFR file/message structure and contents (1/4)

- `bufr_count`: Print the number of messages contained in a BUFR file.

```
$ bufr_count BTEF00012022010100.DC1.DAT  
1519
```

- `bufr_ls`: List select contents from every message contained in a BUFR file.

```
$ bufr_ls BTEF00012022010100.DC1.DAT  
BTEF00012022010100.DC1.DAT  
  
centre          masterTablesVersionNumber  localTablesVersionNumber (→ continued)  
ecmf             27                          0  
ecmf             27  
(↑ continued ↓)  
ecmf             31                          0  
ecmf             21                          0  
1519 of 1519  
messages in BTEF00012022010100.DC1.DAT  
  
1519 of 1519 total messages in 1 files
```

Examine BUFR file/message structure and contents (2/4)

- `bufr_dump`: Print the full content of a BUFR file.

```
$ bufr_dump -p -w count=1 BTEF00012022010100.DC1.DAT
```

```
delayedDescriptorReplicationFactor= {0}  
extendedDelayedDescriptorReplicationFactor= {75}  
edition=3  
masterTableNumber=0  
bufrHeaderSubCentre=0  
bufrHeaderCentre=98  
updateSequenceNumber=0  
dataCategory=2  
dataSubCategory=0  
masterTablesVersionNumber=27  
localTablesVersionNumber=0  
typicalYearOfCentury=22  
(↑ continued ↓)  
observedData=1  
compressedData=0
```

continued ↓)

- `-p`: plan/flat dump
- `-w`: where clause
- `count`: bufr message number

Section 0 (indicator section),
Section 1 (identification section) &
Section 2 (optional section).

Examine BUFR file/message structure and contents (3/4)

- **bufr dump:** Print the full content of a BUFR file.

```
$ bufr_dump -p -w count=1 BTEF00012022010100.DC1.DAT
```

(↑ *continued*)

```
unexpandedDescriptors={
```

```
301128, 007007, 002102, 201133, 025065, 025066, 201000,  
309052, 205011, 005001, 006001, 007001 }
```

Section 3 (data description section).

continued ↓)

Unravelling unexpanded descriptors

→ sequence.def

```
"301128" = [ 001081, 001082, 001083, 001095, 002015, 002016, 002017, 002066, 002067, 002080, 002081,
002082, 002083, 002084, 002085, 002086, 002095, 002096, 002097, 002103, 002191, 025061, 035035 ]
```

→ `element.table`

001081	radiosondeSerialNumber	string	RADIOSONDE SERIAL NUMBER	CCITT IA5	0	0	160	Character	0	20
001082	radiosondeAscensionNumber	long	RADIOSONDE ASCENSION NUMBER	Numeric	0	0	14	Numeric	0	4
001083	radiosondeReleaseNumber	long	RADIOSONDE RELEASE NUMBER	Numeric	0	0	3	Numeric	0	1

...

```
002191|geopotentialHeightCalculation|table|GEOPOTENTIAL HEIGHT CALCULATION|CODE TABLE|0|0|4|CODE TABLE|0|2
025061|softwareVersionNumber|string|SOFTWARE IDENTIFICATION AND VERSION NUMBER|CCITT IA5|0|0|96|Character|0|12
035035|reasonForTermination|table|REASON FOR TERMINATION|CODE TABLE|0|0|5|CODE TABLE|0|2
```



Examine BUFR file/message structure and contents (4/4)

- bufr_dump: Print the full content of a BUFR file.

```
$ bufr_dump -p -w count=1 BTEF00012022010100.DC1.DAT
```

```
(↑ continued)
```

```
radiosondeSerialNumber="2245411/82919"
```

```
(↑ continued ↓)
```

```
#75#timePeriod=4150
```

```
#75#extendedVerticalSoundingSignificance=65536
```

```
#75#pressure=10000
```

```
#75#nonCoordinateGeopotentialHeight=15300
```

```
#75#latitudeDisplacement=0.27636
```

```
#75#longitudeDisplacement=-0.13429
```

```
#75#airTemperature=215.95
```

```
#75#dewpointTemperature=209.75
```

```
#75#windDirection=195
```

```
#75#windSpeed=19
```

```
text="61616 20312"
```

```
#2#latitude=66.77
```

```
#2#longitude=123.4
```

```
heightOfStation=92
```

The BUFR needs to be unpacked to access the following keys.

Section 4 (data section) &
Section 5 (end section).

Rank numbers (e.g. #75#) are used to maintain uniquely identifiable BUFR keys when a descriptor needs to be reused (e.g. sounding profile levels).

Copy BUFR file content

- **bufr_copy**: Copy contents according to specified criteria from an existing BUFR file into a new BUFR file.

```
$ bufr_copy -w count=1 BTEF00012022010100.DC1.DAT BTEF00012022010100_msg1.DC1.DAT
```

This example extracts the first message from the original BUFR and copies it into a new, single-message BUFR.

- -w: where clause
- count: bufr message number



Simple data retrievals and modifications

- **bufr_get**: Print specified contents from BUFR messages.

```
$ bufr_get -p typicalYearOfCentury,typicalMonth,typicalDay,typicalHour,typicalMinute  
BTEF00012022010100.DC1.DAT
```

```
22 1 1 0 24  
22 1 1 0 24  
(↑ continued ↓)  
21 12 31 21 57  
21 12 31 21 50
```

- -p: keys to print
- Multiple keys may be specified in a list, using a comma without spaces.
- Only keys that don't require the BUFR to be unpacked may be retrieved (Sections 0-2).

- **bufr_set**: Sets or changes the value of a key in BUFR messages.

```
$ bufr_set -p bufrHeaderCentre -s bufrHeaderCentre=254 BTEF00012022010100.DC1.DAT  
BTEF00012022010100_bHC254.DC1.DAT
```

- -p: keys to print
- -s: keys/values to set
- Only keys that don't require the BUFR to be unpacked may be modified (Sections 0-2).

Advanced data retrievals and modifications

- **bufr_filter**: Transform BUFR messages using specified rules defined in a 'rules file'.

```
$ bufr_filter -o BTEF00012022010100_statnum.DC1.DAT rules.flt BTEF00012022010100.DC1.DAT
```

→ rules.flt

```
set unpack=1;  
set stationNumber=123;  
set pack=1;  
write;
```

This example sets the key 'stationNumber' equal to 123 in every message.

- -o: output file
- rules.flt: rules file
- Keys that require the BUFR to be unpacked may be also modified.

```
$ bufr_filter -o BTEF00012022010100_latlon.DC1.DAT rules.flt BTEF00012022010100.DC1.DAT
```

→ rules.flt

```
if ((localLatitude >= 30 && localLatitude <= 60) &&  
    (localLongitude >= 0 && localLongitude <= 90)) {  
    write;  
}
```

This example filters every message by a specified latitude-longitude range.

Compare BUFR messages contained in two files

- `bufr_compare`: Print the differences between messages contained in two BUFR files.

```
$ bufr_compare BTEF00012022010100_statnum.DC1.DAT BTEF00012022010100.DC1.DAT  
== 1 == DIFFERENCE == long [stationNumber]: [123] != [343]
```

This example compares the output of our first bufr_filter to the original BUFR.



Additional options

- There are many more additional options that may be used with the CLI tools.
- To see what's available, use '-h'.

E.g.

```
$ bufr_dump -h

NAME      bufr_dump
DESCRIPTION
    Dump the content of a BUFR file in different formats.
(↑ continued ↓)
    -O      Octet mode. WMO documentation style dump.
    -p      Plain/Flat dump (key=value format).
    -d      Dump the expanded descriptors.
    -t      Print type information.
    -f      Force. Force the execution not to fail on error.
    -H      Print octet content in hexadecimal format.
    -a      Dump aliases.
(continued ↓)
```

Test your knowledge (Qs)

→ Search: gov.noaa.ncdc:C01549

→ Download: [Upperair-BUFR_ECMWF_d202201_c20250206.tar.gz](#)

1. Write a bufr_set to make the qualityControl key equal to 100.

```
$
```

2. Write a bufr_get to check that our lat-lon bufr_filter worked as expected.

```
$
```

3. Calculate how many BUFR messages were removed by our lat-lon filter.

```
$
```

Test your knowledge (Q&As)

1. Write a bufr_set to make the qualityControl key equal to 100.

```
$ bufr_set -p qualityControl -s qualityControl=100 BTEF00012022010100.DC1.DAT  
BTEF00012022010100_qc100.DC1.DAT
```

2. Write a bufr_get to check that our lat-lon bufr_filter worked as expected.

```
$ bufr_get -p localLatitude,localLongitude BTEF00012022010100_latlon.DC1.DAT  
  
39.3443 8.96427  
(↑ continued ↓)  
50.5618 10.3771
```

3. Calculate how many BUFR messages were removed by our lat-lon filter.

```
$ bufr_count BTEF00012022010100_latlon.DC1.DAT  
  
246
```

$1519 - 246 = 1273$